

CBV-2U4-3T(-N) Strategy rev1.2

Issue Date: December 12, 2018

Product: CBV-2U4-3T-SI, CBV-2U4-3T-IMP,
CBV-2U4-3T-N-SI, CBV-2U4-3T-N-IMP

Product Version: 1.2

Summary

The **CBV-2U4-3T** and **CBV-2U4-3T-N** strategies have been updated to resolve issues with **CBT-STAT** Setpoint control and **Occupancy** display.

Background

This release being made as part of Cylon’s continuous-improvement policy.

Features and Installation

Resolved issues:

- Setpoints on the **CBV-2U4-3T** and **CBV-2U4-3T-N** can now be changed from the **CBT-STAT**.
- When the **CBV-2U4-3T** or **CBV-2U4-3T-N** goes to “Unoccupied” status, the display on the **CBT-STAT** no longer shows the **setpoints** associated with the “Occupied” status.

Installation

To upgrade existing **CBV-2U4-3T** and **CBV-2U4-3T-N** products,


1. Download the relevant **.CSB** backup file from cylon-automatrix.com/toolbox:

Controller	Strategy Units	Update file
CBV-2U4-3T	Imperial	10020901.CSB
	SI	10030901.CSB
CBV-2U4-3T-N	Imperial	10020801.CSB
	SI	10030801.CSB


2. Use the Site Backup Utility within **CXpro^{HD}** to restore the downloaded **.CSB** file. This will create a **Site** in **CXpro^{HD}** containing a single controller, in which the updated **Strategy** will be housed.




- Right-click on the **controller** in the restored **Site**, and select **Copy Strategy To** :



- In the **Copy Strategy** dialog, select an installed **controller** of the same type as the restored **controller**, and click **Copy**



The updated **Strategy** will then be available for upload on the target **controller**.



Customer Impact

Customers will receive the updated **strategy** with all new orders, and can also download it from cylon-automatrix.com/toolbox. Contact SupportAmericas@cylon.com for further information.